

רבים מלקוחותינו שואלים האם חברת Wonderware מאפשרת להתקין תוכנת אנטי וירוס מחברה כזו או אחרת על מחשבי ה-SCADA וההיסטוריאן

הואיל וישנן אין-ספור תוכנות אנטי-וירוס ואין אפשרות לערוך בדיקה על כל תוכנות אלו, חברת Wonderware מאפשרת לעבוד עם כל תוכנת אנטי וירוס סטנדרטי תוך ההגדרות הבאות:

קבעו את התצורה של תוכנת האנטי-וירוס שלכם כך שתוכנת האנטי-וירוס לא תבצע סריקת של הקבצים והספריות הבאות:

Exclude these ArcestrA folders in a 32-bit system:

C:\ProgramData\ArcestrA\ and all subfolders
C:\Program Files\ArcestrA\
C:\Program Files\Common Files\ArcestrA\
C:\Program Files\FactorySuite\ (The FactorySuite folder may not exist in newer installations)
C:\Program Files\Wonderware\
C:\Users\All Users\Wonderware
C:\InSQL\Data\ (The InSQL folder may not exist in newer installations)
C:\Historian\Data

Exclude these ArcestrA folders in a 64-bit system:

C:\ProgramData\ArcestrA\ and all subfolders
C:\Program Files\Common Files\ArcestrA\
C:\Program Files (x86)\ArcestrA\
C:\Program Files (x86)\Common Files\ArcestrA\
C:\Program Files (x86)\FactorySuite\ (The FactorySuite directory may not exist in newer installations)
C:\Program Files (x86)\Wonderware\
C:\Users\All Users\Wonderware\
C:\Users\Public\Wonderware\
C:\InSQL\Data\ (The InSQL folder may not exist in newer installations)
C:\Historian\Data\

Exclude these folders:

History Store Forward directory in 32- and 64-bit systems:

C:\Users\All Users\ArcestrA\ (default location) Checkpoint directory location default location in a 32-bit system:

C:\Program Files\ArcestrA\Framework\bin\ Checkpoint directory location default location in a 64-bit system:

C:\Program Files (x86)\ArcestrA\Framework\bin\ InTouch HMI Application folder path:

C:\Users\Public\Wonderware\IntouchApplications (default folder path) You can select an application folder path when an InTouch HMI

application is created SMC Logger Storage file path:

C:\ProgramData\ArcestrA\LogFiles\
C:\Documents and Settings\All Users\Application data\ArcestrA\LogFiles\ Exclude these

files from the

C:\Windows\Temp folder: *.aFDX Location of SQL Server database files to be excluded: 32-bit systems:

C:\Program Files\Microsoft SQL Server\MSSQL.MSSQLSERVER\MSSQL\DATA\ (will vary by SQL Server version) 64-bit systems:

C:\Program Files (x86)\Microsoft SQL Server\MSSQL.MSSQLSERVER\MSSQL\DATA\ (will vary by SQL Server version)

Exclude SQL Server database files within this directory of the following types:

.mdf

.ldf

You can also exclude these file types (optional):

*.idx

*.pdx

Exclude the files in the lowest level subfolder of the listed directories in this section.

Antivirus exclusions should not be recursive and should only apply to the lowest listed subfolder in the specified folder path.

הערה חשובה: הנתיבים המפורטים כאן עשויים להיות שונים בהתבסס על ההתקנה הספציפית שלכם. אם אתם משתמשים ב-Wonderware Historian, הקפידו לא לכלול בסריקה את כל התיקיות המכילות את ה History Blocks.



אוסישקין 5, קומה 4, רמת השרון, ישראל, 4721005, 5 Ussishkin St., 4th floor, Ramat Hasharon, Israel, 4721005
מייל: sales@instrumetrics.com, טל: 09-7645820, פקס: 09-7645821